

FRIDGE Documentation

Ryan Stewart

April 2019

1 Introduction

The Fast Reactor Input Deck Generator (FRIDGE) is a tool for designing and building input files for MCNP. It grants the user the ability to create elements, materials, assemblies, and full reactor cores. Currently FRIDGE has the ability to create two types of assemblies; blank and fuel assemblies. A blank assembly can be used to build vacant assemblies in a reactor (to simulate experimental areas or holes from control assemblies). A fuel assembly can be used to build a multiple types of driver assemblies or blanket assemblies. FRIDGE currently contains 24 elements which are most commonly used in the development of fast reactors. Along with this, there are 8 base material for us in FRIDGE. There are also examples of both assembly and core files.

2 Data

2.1 Chart of the Nuclides

To create materials in FRIDGE, the corresponding elements must be present in the directory `fridge/data/CotN`. Each element needs its own YAML file and contains seven variables for inputting data; where each variable and its associated input can be seen in Table 1

Name is a string containing the name of the element. **ZAID** is an integer denoted by $1000 * Z$ (proton or atomic number). **Isotopes** is a list of ZAID's for each isotope in the element denoted by $1000 * Z + N$, where N is the mass number (protons + neutrons) of the isotope. **Abundance** is a list of the natural abundances for the isotopes (this is in weight percent and can be found in any Chart of the Nuclide). Note: for elements with no natural abundances an entry of zero is allowed. The abundance can be set later in the material card. **Mass** is a list of nuclide masses for each isotope listed and is given in amu's. All abundances and masses were obtained using IAEA's Live Chart of Nuclides [1]. **Density** is the density of the natural isotope in g/cc. **Linear Coefficient of Expansion** is the coefficient of thermal expansion and is in units of K^{-1} .

Table 1: Variables for Element YAML file.

Variable Name	Variable Type	Unit	Example
Name	string	–	Silicon
ZAID	integer	–	14000
Isotopes	list of integers	–	[14028, 14029, 14030]
Abundance	list of floats	wt %	[0.92223, 0.04685, 0.0392]
Mass	list of floats	amu	[27.976926, 28.976494, 29.973777]
Density	float	g/cc	2.33
Linear Coefficient of Expansion	float	K^{-1}	0.0

Table 2: Variables for Material YAML file.

Variable Name	Variable Type	Unit	Example
Name	string	–	UO2
Elements	list of str	–	['U', 'O']
ZAIDs	list of ints	–	[92000, 8000]
Weight Fractions	list of floats	wt%	[0.881467, 0.118533]
Enrichment ZAIDs*	list of ints	–	[92000, 8000]
Enrichment Isotopes*	list of list of ints	–	[[92235, 92238], [8016]]
Enrichment Vector*	list of list of floats	wt%	[[0.03, 0.97], [1.0]]
Density	float	g/cc	2.33
Linear Coefficient of Expansion	float	K^{-1}	0.0

*Optional variables if material has specific isotopics.

Table 3: Variables for Blank Assembly YAML file.

Variable Name	Variable Type	Unit	Example
Assembly Type	string	–	Blank
Assembly Pitch	float	cm	12.0
Duct Thickness	float	cm	0.3
Duct Inside Flat to Flat	float	cm	11.1
Assembly Height	float	cm	240
Coolant	string	– LiquidNa	
Assembly Material	string	–	HT9
Blank Height	float	cm	220
Blank Smear	Dictionary	str: wt %	LiquidNa: 0.9, HT9: 0.1
Z Position	float	cm	-60

2.2 Material

Materials can be found in the directory `fridge/data/materials`. Each material in a problem requires its own YAML file and contains five mandatory variables and three optional variables. Where each variable and its associate input can be seen in Table 1

Name is a string containing the name of the element. **Elements** is a list of element symbols to be used in the material. Note: This element symbol is how FRIDGE finds the element in `fridge/data/CotN`, so ensure that the elements exists there and the symbol matches. **ZAIDs** is list of an integers, where each ZAID is denoted by $1000 * Z$ (proton or atomic number). **Weight Fractions** is a list of floats whose entries are the weight fractions associated with the **ZAIDs** above. Note: This value should sum to 1.0. **Enrichment ZAIDs** is a list of ZAIDs whose isotopic fraction is different from the base element. Note: If the isotopic composition is the same as the element in question, the element does not need to be included and it will be created as normal. **Enrichment Isotopes** is a list of lists of isotopic ZAIDs, where each list corresponds to the the **Enrichment ZAIDs** from above. **Enrichment Vector** is a list of lists of weight fractions (enrichment) of each isotope from **Enrichment Vector**. Note: Each list should sum 1.0. **Density** is the density of the natural isotope in g/cc. **Linear Coefficient of Expansion** is the coefficient of thermal expansion and is in units of K^{-1}

2.3 Assembly

There are two types of assemblies that can be built in FRIDGE; blank and fuel assemblies. Both types of assemblies are created using YAML files and can be found in `fridge/data/assembly`. Assembly files for blank and fuel requires a different number of variables; the required variables can be seen in Table 3 and Table 4.

Assembly Type is a string used to denote the types of assembly (blank or fuel). **Assembly Pitch** is a float to denote the distance from the center of one assembly to an adjacent assembly. Note: All assemblies

Table 4: Variables for Fuel Assembly YAML file.

Variable Name	Variable Type	Unit	Example
Assembly Type	string	–	Blank
Assembly Pitch	float	cm	12.0
Duct Thickness	float	cm	0.3
Duct Inside Flat to Flat	float	cm	11.1
Assembly Height	float	cm	240
Coolant ^{*,**}	string	– LiquidNa	
Assembly Material	string	–	HT9
Pins Per Assembly	int	–	271
Pin Diameter	float	cm	0.53
Clad Thickness	float	cm	0.037
Fuel Smear [†]	float	%	0.75
Fuel Diameter [†]	float	cm	0.5
Pitch	float	cm	0.661
Wire Wrap Diameter	float	cm	0.126
Wire Wrap Axial Pitch	float	cm	2.0
Fuel Height	float	cm	60
Fuel	str	–	UO2
Clad	str	–	HT9
Bond	str	–	LiquidNa
Bond Above Fuel [*]	float	cm	0.6
Plenum Height	float	cm	220
Plenum Smear	dictionary	str: wt %	LiquidNa: 0.5, HT9: 0.25, Void: 0.25
Reflector Height	float	cm	220
Reflector Smear	dictionary	str: wt %	LiquidNa: 0.5, HT9: 0.25, Void: 0.25

[†] Either fuel smear or fuel diameter can be used.

^{*} Optional

^{**} Required if building a single assembly.

in a core should have the same assembly pitch; if they don't errors in geometry may arise. **Duct Thickness** is a float to denote the thickness of the assembly duct. **Duct Inside Flat to Flat** is a float to denote the distance from one side of a hexagon to the other. **Assembly Height** is a float used to denote the total height of the assembly. **Coolant** is a string used to create a material for the coolant. **Assembly Material** is a string used to create a material for the assembly. **Blank Height** is a float used to denote the height of the blank portion of the assembly. Note: If **Blank Height** of the assembly exceeds the **Assembly Height**, the **Assembly Height** will truncate the **Blank Height**, this may lead to geometry errors. **Blank Smear** is a dictionary of strings and weight percents. This will create a smeared material where each string in the dictionary will create a material, whose weight fraction is the corresponding float. **Z Position** is a float which allows the user to manually adjust where they want the bottom of the blank assembly to be.

Assembly Type is a string used to denote the types of assembly (blank or fuel). **Assembly Pitch** is a float to denote the distance from the center of one assembly to an adjacent assembly. Note: All assemblies in a core should have the same assembly pitch; if they don't errors in geometry may arise. **Duct Thickness** is a float to denote the thickness of the assembly duct. **Duct Inside Flat to Flat** is a float to denote the distance from one side of a hexagon to the other. **Assembly Height** is a float used to denote the total height of the assembly. **Coolant** is a string used to create a material for the coolant. **Assembly Material** is a string used to create a material for the assembly. **Pins Per Assembly** is an integer of the number of pins for the assembly. Note: This number should fit an exact number of rings required, Table 5, shows pins are required for a given number of rings.

Pin Diameter is a float which is the diameter of the fuel pin (outside of the cladding). **Clad Thickness** is a float to denote the cladding thickness. **Fuel Smear** is a float to denote the percentage of area inside the cladding that the fuel encompasses, the relation between the fuel diameter and fuel smear can be seen

Table 5: Hexagonal Rings to Pins/Assemblies.

Number of Rings	Number of Pins/Assemblies
One	1
Two	7
Three	19
Four	37
Five	61
Six	91
Seven	127
Eight	169
Nine	217
Ten	271
Eleven	331

Table 6: Variables for Core YAML file.

Variable Name	Variable Type	Unit	Example
Name	string	–	TestCore
Vessel Thickness	float	cm	10.0
Vessel Material	string	–	HT9
Coolant Material	string	–	LiquidNa
Assembly Positions	dictionary	str: str	01A01: TestAssembly

below, where R_{IC} is the inner cladding radius, and A_{fuel} is the **Fuel Smear**.

$$R_{fuel} = \sqrt{\%A_{fuel}R_{IC}} \quad (1)$$

Fuel Diameter is a float to denote the diameter of the fuel slug. **Pitch** is a float to denote the distance from the center of one fuel pin to an adjacent fuel pin. **Wire Wrap Diameter** is a float to denote the diameter of the wire wrap. Note: The diameter of the pin plus the diameter of the wire wrap should not exceed the pitch. FRIDGE will allow this, but it is not physically possible. **Wire Wrap Axial Pitch** is a float which denotes the distance between each wrap. **Fuel Height** is a float to denote the height of the fuel pin. **Fuel** is a string to denote the fuel material. **Clad** is a string to denote the cladding material. **Bond** is a float to denote the fuel bond material. **Bond above Fuel** is a float to denote the height of the bond above the fuel. **Plenum Height** is a float used to denote the height of the plenum portion of the assembly. **Plenum Smear** is a dictionary of strings and weight percents. This will create a smeared material where each string in the dictionary will create a material, whose weight fraction is the corresponding float. **Reflector Height** is a float used to denote the height of the reflector portions of the assembly. **Reflector Smear** is a dictionary of strings and weight percents. This will create a smeared material where each string in the dictionary will create a material, whose weight fraction is the corresponding float.

2.4 Core

A core is built by placing any number of assemblies into any position within the core. It is created using a YAML file, which can be found in **fridge/data/core** and requires four variables in addition to n number of assembly positions. 6 shows the requirements for a core file.

Name is a string used to denote the name of the core. **Vessel Thickness** is a float do denote the thickness of the vessel both axially and radially. **Vessel Material** is a string used to create a material for the reactor vessel. **Coolant Material** is a string used to create the coolant for the reactor vessel. Note: This will overwrite any coolant material assigned to an assembly. **Assembly Position** is used to describe each assembly in the core, and what assembly goes there. The first entry is a five character string which broken into a triplet. The first two number denote the ring, the letter denotes the hexant, and the last two




Figure 1: Description of assembly positions.

numbers denote the number of assemblies off the hexant axis. Figure 1, shows the nomenclature used to describe each position.

2.5 FRIDGE Input File

The FRIDGE input file is used to denote general properties for the MCNP input file, and what core/assembly to make, these files can be found in `fridge/fridge_input_files`. There are currently 16 options that can be included in the FRIDGE input file, Table 7 gives a descriptions of each one and the default value.

The only variables required for building a FRIDGE input file are the **Name** and **Input Type**, all other variables have default setting. The **Name** is assembly or core file which will be used. The **Input Type** is the type of file to be create, two options are available; Single and Core. **Output File Name** will denote the name of the MCNP input file, `.i` file, that will be created. **Temperature** is the temperature of the system denoted in Kevlin, currently there are three options; 600, 900, and 1200. **XC Library** is the name of the cross section library that will be used, currently there are three options; ENDFVII.0, ENDFVII.1, JEFF3.1. Note: The combination of **Temperature** and **XC Library** will select the appropriate cross-section set for each material used. **Number of Generations** is the MCNP number of generations that the simulation will run for. **Number of skipped Generations** is the MCNP number of generations that are skipped before statistics are started. **Number Particles per Generation** is the number of particles that will be run for each generation. **Run Kinetics** will implement the `kopts` portion of code for MCNP, the default setting for `kopts` are currently used. The remaining settings are currently not used in FRIDGE, but are intended for addition. A description of each will be added as each variable is added.

Table 7: Variables for FRIDGE Input YAML file.

Variable Name	Variable Type	Unit	Example	Default
Name	string	–	FRIDGE_Test	
Input Type	string	–	Core	Single
Output File Name*	string	–	File23	FRIDGE1
Temperature*	int	K	1200	900
XC Library*	string	–	ENDFVII.0	ENDFVII.1
Number of Generations*	int	–	1000	230
Number of Skipped Generations*	int	–	50	30
Number of Particle Per Generations*	int	–	1e8	1e6
Run Kinetics*	Boolean	–	True	False
Void Percent*	float	%	0.1	1.0
ksens*,**	Boolean	–	True	False
Temperature Adjusted Density*,**	Boolean	–	True	False
Temperature Adjusted Volume*,**	Boolean	–	True	False
Smear Clad*,**	Boolean	–	True	False
Smear Bond*,**	Boolean	–	True	False

* Optional

** Currently not built into FRIDGE.

3 Test Suite

FRIDGE has an a test suite built that can be run to ensure all of the packages are operating correctly. To run the test suite, open a terminal in the fridge directory and perform the following:

```
python -m pytest
```

This should run all of the files in `fridge/test_suite`. There are currently 82 tests which need to be run. This will generate four MCNP input files in `fridge/mcnp_input_files`. Note: There are four MCNP input files with the preface `Prefab_`, these are the MCNP input files that the test suite is checking against. DO NOT alter these files in any way.

3.1 Fuel Assembly Example

An few example fuel assemblies can be seen in `fridge/data/assembly`. This example will look at the `EBRII_MKII` assembly. This assembly has the following attributes, which can be seen in Table 8.

Table 8: Variables for Fuel Assembly YAML file.

Variable Name	EBR-II MK-II Assembly
Assembly Type	Fuel
Assembly Pitch	5.887
Duct Thickness	0.2032
Duct Inside Flat to Flat	5.6134
Assembly Height	164.386
Coolant	LiquidNa
Assembly Material	SS316
Pins Per Assembly	91
Pin Diameter	0.4420
Clad Thickness	0.0305
Fuel Diameter	0.3302
Pitch	0.566
Wire Wrap Diameter	0.124
Wire Wrap Axial Pitch	15.24
Fuel Height	34.29
Fuel	U
Clad	SS316
Bond	LiquidNa
Bond Above Fuel	1.31
Plenum Height	28.3
Plenum Smear	LiquidNa: 0.50, Void: 0.25, SS316: 0.25
Reflector Height	61.3537
Reflector Smear	LiquidNa: 0.116, 0.884

The inputs from 8 create an assembly similar to the MK-II driver assemblies found in EBR-II, as referenced in [2], where Figures 2 - 4 show the MCNP assembly. In Figure 2 the regions are, from bottom to top; lower reflector, fuel, plenum and upper reflector. In 3, we see the impact of including the variable **Bond Above Fuel**, which adds the bond material (blue) above the fuel (purple). Figure 4 shows the 91 pins in the assembly; there is fuel (purple), bond (blue), clad (yellow), wire wrap + coolant mixture (green), excess coolant (light blue), and the hex duct (maroon).

4 Running FRIDGE

Running FRIDGE is best done in an interactive python terminal (such as ipython). Once an Ipython terminal is open in the `fridge` directory, import `fridge_driver` as follows:

```
import fridge.driver.fridge_driver as fd
```

To run a FRIDGE input file, run the `main` program with the input file name as a string input, as seen below. Note: You do not include the file type.

```
fd.main('<input file name>')
```

For example the EBR-II assembly that was created in the previous section can be run as follows:

```
fd.main('EBR-II_Driver')
```

Users can now continue to make material, assembly, core, and FRIDGE input files. These corresponding MCNP input files will be listed in `/fridge/mcnp_input_files/` with the given output file name specified in the FRIDGE input file.



Figure 2: View of entire length of an EBRII assembly.




Figure 3: Sodium above fuel height.




Figure 4: Fuel region of EBR-II assembly.

References

- [1] "Livechart - Table of Nuclides - Nuclear structure and decay data", [Www-nds.iaea.org](https://www-nds.iaea.org/relnsd/vcharthtml/VChartHTML.html), 2019. Available: <https://www-nds.iaea.org/relnsd/vcharthtml/VChartHTML.html>. [Accessed: 01- May- 2019].
- [2] E. Lum, C. Pope, R. Stewart, B. Byambadorj, and Q Beaulieu, *Evaluation of Run 138B At Experimental Breeder Reactor II, A Prototypic Liquid Metal Fast Breeder Reactor*, International Handbook of Evaluated Reactor Physics Benchmark Experiments, 2018.